

Proper Mixing Order



America's VM Specialists

13 North 8th Street,
Opelika, AL 36801, USA
www.alligare.com • 888-255-4427

STEP 1	Fill clean spray tank 1/2 to 2/3 of desired level with clean water and begin agitation.	STEP 7	Add any flowable liquids (FL) or suspension concentrates (SC); e.g. ALLIGARE DIURON 4L .
STEP 2	Add any water conditioner; e.g. ALLIGARE WATER CONDITIONER, ALLIGARE WATER CONDITIONER SU .	STEP 8	Add any emulsifiable concentrates (EC) e.g. ALLIGARE 2,4-D LV6, ALLIGARE TRICLOPYR 4, BOULDER 6.3, CLEARGRAZE™, FLAGSTAFF™, and TRIUMPH® XTR .
STEP 3	Add any wettable powders (W, WP); Note: a slurry should always be made with wettable powders, water dispersible granules or dry flowables before adding to the tank.	STEP 9	Add any emulsion oil in water (EW) or suspension emulsion (SE) formulations;
STEP 4	Add any water dispersible granules (WG, WDG) or dry flowables (DF); e.g. ALLIGARE MSM 60, ALLIGARE CHLORSULFURON 75, LARAMIE 25DF, PROMENADE™ .	STEP 10	Fill tank almost to capacity.
STEP 5	Add any oil dispersion formulations (OD).	STEP 11	Add any soluble liquids (SL) or soluble granules (SG); e.g. ALLIGARE GLYPHOSATE 4 PLUS, ALLIGARE GLYPHOSATE 5.4, DRYPHOSATE 75 SG, IMOX™ .
STEP 6	Be certain all materials added are fully dispersed before proceeding further.	STEP 12	Add other adjuvants and fill the tank; e.g. ALLIGARE 90, ALLIGARE OSS/NIS SURFACTANT , Add any oils last in all mixtures; e.g. ALLIGARE MSO, ALLIGARE MSO WEST, ALLIGARE MVO PLUS .



For more information on Alligare products or to find a regional specialist near you, call 888-255-4427 or visit alligare.com. Check with your Alligare regional specialist for product state registration status.

CLEARGRAZE, FLAGSTAFF, IMOX, PROMENADE and TRIUMPH are trademarks of ADAMA Group Company

